


Script workflow



Installation

Create environment:

```
git clone https://github.com/brent88310070/CRE_finding.git
cd CRE_finding
conda env create -f environment.yml
conda activate cre
```

Install MEME package:

```
wget https://meme-suite.org/meme/meme-software/5.5.8/meme-5.5.8.tar.gz
tar xzf meme-5.5.8.tar.gz
cd meme-5.5.8
./configure --prefix=$HOME/meme --enable-build-libxml2 --enable-build-libxslt
make
make install
echo 'export PATH=$HOME/meme/bin:$HOME/meme/libexec/meme-5.5.8:$PATH' >
~/miniconda3/envs/cre/etc/conda/activate.d/env_vars.sh
```

下載SRR檔案 (Fastq)

Download raw data:

```
./download.sh
```

Parameter and threshold

SRR_LIST="srr_list.txt"

SRR ID 清單檔案

BASE_DIR="raw_data"

儲存資料夾

THREADS=8

fasterq-dump 使用的執行緒數

KEEP_SRA=false

若要保留 .sra 檔，改成 true

```
srr_list.txt
```

```
SRP059724_Ara_root  
SRR21710377  
SRR21710378  
SRR21710379  
SRR21710380  
SRR21710381  
SRR21710382  
SRR21710383  
SRR21710384
```

] Project name

] SRR ID of files you want to download

Fastq 轉成 BAM files

Fastq to BAM files:

```
./toBAM.sh
```

Parameter and threshold

INPUT_PREFIX="SRP551342_tomato"

TISSUE="root"

BASE_DIR="raw_data"

GENOME_DIR="./ref/S_lycopersicum/star_index"

THREADS=12

PAIRED=true

GZIP_FASTQ=false

專案/實驗前綴

子資料夾名稱，可留空

儲存主資料夾

STAR 索引路徑

STAR 執行緒數

true=雙端定序；false=單端定序

若為 *.fastq.gz 請設 true

若沒有star_index，需從gtf轉star_index:

```
STAR --runThreadN 8 \
```

```
--runMode genomeGenerate \
```

```
--genomeDir star_index \
```

```
--genomeFastaFiles S_lycopersicum_chromosomes.4.00.fa \
```

```
--sjdbGTFfile ITAG4.1_gene_models.gtf \
```

```
--sjdbGTFtagExonParentTranscript Parent \
```

```
--sjdbOverhang 99
```

BAM files 轉成 Feature count files

BAM files to Feature count files:

```
./to_featureCounts.sh
```

Parameter and threshold

INPUT_PREFIX="SRP551342_tomato"

TISSUE="root"

THREADS=12

GTF="ref/S_lycopersicum/S_lycopersicum.gtf"

IS_PAired=true

專案名稱

子資料夾名稱

使用的執行緒數

註解檔案 (GTF)

是否為 paired-end 資料

SRR ID轉成GEO Accession ID & 合併相同的GEO Accession ID

Process same project dataset & Combine same GEO data:

```
python combine_geo_data.py
```

Parameter and threshold

```
file_name = './SRP399644_tomato_root_count/SRP399644_tomato_counts.txt'
```

```
output_name = './exp_files/SRP399644_tomato_root_exp.tsv'
```

```
meta_path = 'run_info.txt'
```

featureCounts 輸出

最終輸出檔案

需包含 SRR 對 GEO ID 的對照表

Run	time_points	Organism	tissue	treatment	GEO_Accession (exp)
SRR2932437	10 day	Arabidopsis thaliana	root	Pi sufficiency	GSM1936695
SRR2932438	10 day	Arabidopsis thaliana	root	Pi sufficiency	GSM1936695
SRR2932455	10 day	Arabidopsis thaliana	root	Pi sufficiency	GSM1936704
SRR2932456	10 day	Arabidopsis thaliana	root	Pi sufficiency	GSM1936704
SRR2932461	1 day	Arabidopsis thaliana	root	Pi starvation	GSM1936707
SRR2932462	1 day	Arabidopsis thaliana	root	Pi starvation	GSM1936707
SRR2932443	1 day	Arabidopsis thaliana	root	Pi starvation	GSM1936698
SRR2932444	1 day	Arabidopsis thaliana	root	Pi starvation	GSM1936698
SRR2932449	3 day	Arabidopsis thaliana	root	Pi starvation	GSM1936701
SRR2932450	3 day	Arabidopsis thaliana	root	Pi starvation	GSM1936701
SRR2932467	3 day	Arabidopsis thaliana	root	Pi starvation	GSM1936710

每個Project 需要跑一次，ex: Project name SRP399644
run_info.txt須包含Run & GEO_Accession (exp) 這兩行
其他行，可有可無

DEG analysis: 將不同實驗的Control & Treatment進行DEG分析

After merging the expression data of the same species, DEG analysis was performed:

```
python deg_analysis.py
```

```
# Parameter and threshold
```

```
# --- 合併 expression 檔 ---
```

```
input_folder = "./exp_files/tomato"
```

```
file_pattern = "*.tsv"
```

```
index_col = "Geneid"
```

```
merged_counts = "./exp_files/Tomato_all_exp.tsv"
```

```
# --- DESeq2 相關 ---
```

```
sample_info_path = "./read_treat_control_list.txt"
```

```
deg_output_dir = "./tomato_deg_results"
```

```
# 單實驗 expression 檔資料夾
```

```
# 檔案格式
```

```
# 基因欄位名稱
```

```
# Treatment/Control 配對設定
```

```
# DESeq2 輸出資料夾
```

可以先在Excel檔編輯:
Excel檔中的格式如右，然後複製
到read_treat_control_list.txt

SRP551342_tomato	Control	GSM8680620	GSM8680619	GSM8680618	
	Treatment	GSM8680611	GSM8680610	GSM8680609	
SRP399644_tomato_2cm	Control	GSM6600867	GSM6600866	GSM6600865	GSM6600864
	Treatment	GSM6600871	GSM6600870	GSM6600869	GSM6600868
SRP399644_tomato_1cm	Control	GSM6600859	GSM6600858	GSM6600857	GSM6600856
	Treatment	GSM6600863	GSM6600862	GSM6600861	GSM6600860

DEG summary

DEG summary & get promoter: 整合不同DEG lists的結果

Combine several DEG lists (DEG summary) & get promoter:

```
./deg_summary_and_get_promoter.sh
```

```
# Parameter and threshold
```

```
# — Step-1 : 合併各樣本 DEG 結果 —————
```

```
INPUT_DIR="./tomato_deg_results"    # 存放多個 *.tsv
```

```
PADJ_TH=0.05                        # FDR 門檻
```

```
FC_TH=1                             # |log2FC| 門檻
```

```
# — Step-2 : 篩選嚴謹 DEG / Non-DEG —————
```

```
SPECIES="tomato"                    # 也會作為檔名前綴
```

```
SIG_COUNT=2                         # sig_count ≥ ?
```

```
DEG_FC_TH=1                         # meta_log2FC > ?
```

```
NON_P_TH=0.1                       # Non-DEG 的 meta_p > ?
```

```
NON_FC_NEAR0_TH=0.1                # |meta_log2FC| ≤ ?
```

```
# — Step-3 : 擷取啟動子序列 —————
```

```
PROMOTER_UP_BP=1000                # 1000 或 2000
```

```
NEG_MULTIPLIER=3                    # 每個 positive 配幾個 negative，3代表neg是pos數量的三倍
```

```
NEG_MIN=1000                        # 至少多少條 negative
```

```
GFF_PATH="ref/S_lycopersicum/ITAG4.1_gene_models.gff"
```

```
FASTA_PATH="ref/S_lycopersicum/S_lycopersicum_chromosomes.4.00.fa"
```

使用STREME來找motifs

Find motif by STREME:

```
./run_motif.sh
```

POS=arabidopsis_DEG_promoter_1kb.fa	# Positive sample
NEG=arabidopsis_nonDEG_promoter_1kb.fa	# Negative sample
OUT=motif_out	# output director
OUT_DIR=Arabidopsis	# sub director
MINW=6	# short motif length
MAXW=15	# longer motif length
N_MOTIFS=20	# motif number

```
streme_xml_to_html 出問題，需安裝: sudo apt-get install libxml-parser-perl
```

CRE summary

取得每個實驗 DEG analysis的 DEG以及non DEG的 Promoter

Get and filter DEG & non DEG in each experiments and promoter:

```
./extract_multi_expt_DEG_and_promoter.sh
```

```
# Parameter and threshold
```

```
# 1) DEG / non-DEG GeneID 清單 (extract_multi_expt_DEG_and_nonDEG.py)
```

```
INPUT_DIR="./tomato_deg_results"
```

```
# 存放 DESeq2 .tsv 的目錄
```

```
OUTPUT_DIR="./multi_exp_tomato"
```

```
# 產出清單的根目錄
```

```
FILE_PATTERN="*.tsv"
```

```
# 要讀取的檔案格式
```

```
BASEMEAN_DEG_MIN=10
```

```
# DEG 條件
```

```
LOG2FC_DEG_MIN=1
```

```
PADJ_DEG_MAX=0.05
```

```
LOG2FC_NON_MAX=0.1
```

```
# non-DEG 條件
```

```
PADJ_NON_MIN=0.1
```

```
PROMOTER_UP_BP=1000
```

```
# 1000 或 2000
```

```
NEG_MULTIPLIER=3 # 每個 positive 配幾個 negative
```

```
# 2) Promoter 擷取 (extract_multi_expt_promoter.py)
```

```
GFF_PATH="ref/S_lycopersicum/ITAG4.1_gene_models.gff"
```

```
FASTA_PATH="ref/S_lycopersicum/S_lycopersicum_chromosomes.4.00.fa"
```

```
PROMOTER_UP_BP=1000
```

```
# 1000 = -1 kb , 2000 = -2 kb ...
```

```
DEG_FILENAME="DEG.txt"
```

```
# 若改名請同步修改
```

```
NONDEG_FILENAME="nonDEG.txt"
```

使用STREME來找每個實驗的motifs

Find motif by STREME:

```
./run_multi_expt_motif.sh
```

ROOT_DIR="./multi_exp_tomato"	# ← 放各 sample 子資料夾的根目錄
PROM_SIZE="1kb"	# "1kb" / "2kb"... (檔名必須含此字串)
MINW=5	# 最短 motif 長度
MAXW=15	# 最長 motif 長度
N_MOTIFS=20	# 要找幾個 motif
VERBOSITY=1	# streme --verbosity

```
streme_xml_to_html 出問題，需安裝: sudo apt-get install libxml-parser-perl
```

整合不同實驗的motif，並移除冗餘motifs

Summary CREs & remove redundant motifs:

```
python cre_integrate.py
```

```
# Parameter and threshold for cre_integrate.sh
```

```
# — 資料來源與去冗餘後輸出 —
```

```
DATA_DIR = "./multi_exp_tomato"
```

```
FILTERED_MEME = f"{DATA_DIR}/filtered.meme"
```

```
KEPT_ID_TSV = f"{DATA_DIR}/kept_motif_ids.tsv"
```

```
REDUNDANT_TSV = f"{DATA_DIR}/redundant_motif_reps.tsv"
```

```
# — 參數設定 —
```

```
EVALUE_FILTER = 10.0
```

```
TOMTOM_THRESH = 0.05
```

```
# — Logo 繪圖 —
```

```
N_LOGO_MOTIFS = 5
```

```
LOGO_OUT_DIR = f"{DATA_DIR}/motif_logos"
```

```
N_REP_LOGOS = 5
```

```
REP_LOGO_DIR = f"{DATA_DIR}/reps_motif_logos"
```

```
FIGSIZE = (4, 1.5)
```

```
DPI = 200
```

```
COLOR_SCHEME = "classic"
```

```
# 多個實驗資料夾
```

```
# STREME motifs：保留  $E \leq 10$ 
```

```
# Tomtom q-value 閾值
```

```
# filtered.meme 前 N 個
```

```
# 代表 motif 前 N
```

```
# 單圖尺寸 (inch)
```

```
# 解析度
```

```
# Logomaker 色盤
```

```
畫Top N motif
```

```
畫Top N repeat motif
```

Cross species motif summary

整合在不同物種皆出現的motifs

Cross species motif summary (two species):

```
python cross_species_motif_cre_summary.py
```

```
# Parameter and threshold
```

```
SUMMARY_TYPE = "deg_summary"          # 或 "cre_summary"
```

```
TOMTOM_THRESH = 0.05                  # Tomtom q-value 上限
```

```
TEMP_DIR      = "tomtom_cross_temp"    # Tomtom 暫存資料夾
```

```
OUT_DIR       = "cross_species_motif"
```

```
if SUMMARY_TYPE == "deg_summary":
```

```
    SPECIES1_FILE = "./motif_out/arabidopsis_1kb_sig_count_6/streme.txt"
```

```
    SPECIES2_FILE = "./motif_out/tomato_1kb_sig_count_1/streme.txt"
```

```
    CRE_DIR = os.path.join(OUT_DIR, "deg_summary")
```

```
elif SUMMARY_TYPE == "cre_summary":
```

```
    SPECIES1_FILE = "./multi_exp_arabidopsis/filtered.meme"
```

```
    SPECIES2_FILE = "./multi_exp_tomato/filtered.meme"
```

```
    CRE_DIR = os.path.join(OUT_DIR, "cre_summary")
```

```
OUT_TSV       = os.path.join(CRE_DIR, "repeat_motif_cross_species.tsv")
```